



System Settings | Card Program Setup



Datamatic cannot accept any responsibility, financial or otherwise, for any consequences arising out of the use of this material. The information contained herein is subject to change. Revisions may be issued to advise of such changes or additions. The information and techniques contained in this document are the property of Datamatic and may not be disclosed in total or in part without the written permission of Datamatic.

TABLE OF CONTENTS

CARD PROGRAM SETUP	3
Overview	3
Add Card Program.....	4
Edit Card Program.....	6
Delete Card Program.....	7

CARD PROGRAM

Overview

The **Card Program** defines each Card Type (ATM, Debit, and Credit) offered by the credit union and the sub-programs within each. This would be used by credit unions using a card maintenance interface through their vendor. For example, the credit union could have Platinum Visa Debit Cards and Regular Visa Debit Cards. Standard Debit Cards and HSA Debit Cards could be offered. This would be used by credit unions doing card maintenance through their vendor.

This window allows a way to assign credit union friendly names to Debit/Credit Card Account Number ranges. This will reduce errors by the staff in assigning an incorrect card number. In addition, since the system knows the account number range, an account number can be automatically assigned with a random unused account number. The system will be able to profile the different card maintenance vendor options that are used for each card program.

The Card Program Folder is located in [\[Main Ribbon > System Settings > Card Program Setup\]](#).



System Settings - Card Programs


ID	DESCRIPTION	TYPE	FORMAT	BIN	HOST ID	CARD ACCESS	LIMIT GROUP	INSTANT ISSUE	PBF
1	Regular Debit Card	Debit	COOP-CAF	333344	AAABB	MMMMMMM	AACF02	Yes	Yes
2	Premium Debit Card	Debit	COOP-CAF	444488	AAACC	NNNNNNN	AACL04	Yes	Yes
3	Premium Credit Card	Credit	VANTIV	777733	CCCAA	AAAAAAA	BBDH14	Yes	Yes
4	Gold Credit Card	Credit	VANTIV	226622	CCDDD	BBBBBBB	BBDL17	Yes	Yes
5	ATM only	ATM	COOP-CAF	888811	FFFWW	KKKKKKK	KKR993	Yes	Yes
6	Debit Card	Debit	COOP-CAF	333344	AAADD	OOOOOOO	AADL05	Yes	Yes

PIN OFFSET	REISSUE MONT	STARTING PAN	ENDING PAN	CONTROL NUMBER	LIMIT 1	LIMIT 2	LIMIT 3	LIMIT 4
36	100	100	999999	94				
48	200	200	999999	44				
24	300	300	999999	15				
36	400	400	9999999	16				
36	500	500	9999999	23				
36	200	200	999999	95				

Add Card Program

The **Add Card Program** screen displays the information needed to create a new card program. User can launch Add Card Program screen by using the following:

Click	Shortcut Key
	



The screenshot shows the 'Add Card Program' window with the following fields:

- Description:
- Control Number:
- Host ID:
- Limit Group:
- Limit 1:
- Limit 3:
- EMV:
- PIN Offset:
- BIN:
- Starting PAN:
- Type:
- File Format:
- Card Access:
- Limit 2:
- Limit 4:
- PBF:
- Re-Issue Months:
- Ending PAN:

An 'OK' button is located at the bottom right of the window.

Field	Comments
Description	Credit Union defined
Type	Type of card
	ATM
	Debit
	Credit
Control Number	Defined by Vendor
File Format	Vendor
	COOP-CAF
	VANTIV
	FIS
	Shazam
	PSCU

Field	Comments
	ELAN
Host ID	Defined by Vendor
Card Access	Defined by Vendor
Limit Group	Defined by Vendor
Limit 1	Card Limit as defined by Vendor
Limit 2	Card Limit as defined by Vendor
Limit 3	Card Limit as defined by Vendor
Limit 4	Card Limit as defined by Vendor
EMV	Chip card indicator
	No
	Yes
PBF	Positive Balance File indicator
	No
	Yes
PIN Offset	Defined by Vendor
	Card
	Processor
	First
Re-issue Months	Number of months to advance expiration date on auto reissued cards
BIN	BIN Number (1 st 6 digits) of PAN numbers for this program
Starting PAN	Start range (digits 7-15) for automatic assigned PAN
End PAN	End range (digits 7-15) for automatic assigned PAN

Edit Card Program

The **Edit Card program** screen allows user to modify Card Program information. The screen can be launched by:

Double Click	Shortcut Key
Item	Enter

Datamatic VIEW
✕

Edit Card Program
📄 🖨️

Description:	Premium Debit Card	Type:	Debit ▾
Control Number:	42	File Format:	COOP-CAF ▾
Host ID:	AAACC	Card Access:	NNNNNNN
Limit Group:	AACL04		
Limit 1:		Limit 2:	
Limit 3:		Limit 4:	
EMV	Yes ▾	PBF	Yes ▾
PIN Offset:	Card ▾	Re-Issue Months:	48
BIN:	444488		
Starting PAN:	200	Ending PAN:	999999

OK

Delete Card Program

Deleting a program removes the program from the card program screen. Programs can be deleted by:

